3GPP TR 23.811 V8.0.0 (2008-03)

Technical Report

3rd Generation Partnership Project; Technical Specification Group Services and System Aspects; Service level interworking for messaging services; Stage 2 (Release 8)



The present document has been developed within the 3rd Generation Partnership Project (3GPP TM) and may be further elaborated for the purposes of 3GPP.

Keywords
UMTS, SMS, interworking

3GPP

 $Postal\,address$

3GPP support office address

650 Route des Lucioles - Sophia Antipolis Valbonne - FRANCE Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Internet

http://www.3gpp.org

Copyright Notification

No part may be reproduced except as authorized by written permission. The copyright and the foregoing restriction extend to reproduction in all media.

@ 2008, 3GPP Organizational Partners (ARIB, ATIS, CCSA, ETSI, TTA, TTC). All rights reserved.

Contents

Forew	vord	5
Introd	luction	5
1	Scope	<i>6</i>
2	References	<i>6</i>
3	Definitions and abbreviations	_
3.1	Definitions and aboreviations	
3.1 3.2	Abbreviations	
4	Overall requirements	
5	Scenarios for service-level interworking	
5.1	General	
5.2	Capability of the UE	
5.3	Use cases	
5.3.1	IM user with non SMS capable UE receives short message from an SMS user	
5.3.2	IM user with non SMS capable UE sends an Instant Message to an SMS user	
5.3.3	IMS user with delivery preferences/operator policy set to SMS for receiving messages	
5.3.4	Concatenated SMS messages delivered as an IM large message	
5.3.5	IM large message delivered as concatenated SMS messages	
5.3.6	IM user with delivery preferences set to SMS for large messages	
5.3.7	Prevention from being interworked	
5.3.8 5.3.9	IM user sends an Instant Message to an SMSIP UESMSIP UE sends an encapsulated Short Message to an IM user with non SMS capable UE	
5.3.10	· · · · · · · · · · · · · · · · · · ·	
5.3.10	AS addressed by PSI receives short message from an SMS user	
5.3.11 5.4	Scenarios	
5.4.1	Scenario 1: IMS origination and SMS termination to the SMS UE with the service level	10
	interworking in the originating side	10
5.4.2	Scenario 2: IMS origination and SMS termination to the SMS UE with the service level	
	interworking in the terminating side	10
5.4.3	Scenario 3: SMS origination from the SMS UE and IMS termination	
5.4.4	Scenario 4: SMSIP UE sends an encapsulated Short Message to an IM user	
5.4.5	Scenario 5: IMS origination and SMS termination to the SMSIP UE with the service level	
	interworking in the terminating side	12
6	Architectural requirements	12
7	Architecture alternatives	14
7.1	Alternative 1	14
7.1.1	Architectural details	
7.1.1.1	Reference architecture	14
7.1.1.2		
7.1.1.3		
7.1.1.4		
7.1.1.4		
7.1.1.4	<u> </u>	
7.1.1.4		
7.1.1.4 7.1.1.4	IMS registered user with delivery preferences/operator policy set to SMS for receiving short	
	messages	
7.1.1.4		
7.1.1.4	·	
7.1.1.4		
7.1.1.4	• 1	
7.1.1.4 7.1.2	I.10 IM capable UE sends an IM to an SMS user with Interworking in the terminating side	25 26
1 1 /.	HIDACI	/.r

7.1.3	Assessment	26
7.2	Alternative 2	27
7.2.1	Architectural details	
7.2.1.1	Reference architecture	27
7.2.1.2	Reference points	27
7.2.1.2.1	My Reference Point	27
7.2.1.3	Functional Entities IP-SM-GW	28
7.2.1.4	Procedures	28
7.2.1.4.1	IM user sends an Instant Message to an SMS user	28
7.2.1.4.2	IM user receives short message from an SMS user	29
7.2.1.4.3	Concatenated SM messages delivered as an IM large message	29
7.2.1.4.4	Status Report procedure for Instant Message to SMS message interworking	29
7.2.1.4.5	IMS registered user with delivery preferences/operator policy set to SMS for receiving short	
	messages	29
7.2.1.4.6	Delivery to unregistered subscriber	29
7.2.1.4.7	AS addressed by PSI receives short message from an SMS user	29
8 Co	onclusion	30
Annex A	: IM user sends an Instant Message to a group list including SMS users	31
Anne x B	: Relationship between SMSIP and SMS-IM Interworking	33
Annex C	C: Change history	36

Foreword

This Technical Report has been produced by the 3rd Generation Partnership Project (3GPP).

The contents of the present document are subject to continuing work within the TSG and may change following formal TSG approval. Should the TSG modify the contents of the present document, it will be re-released by the TSG with an identifying change of release date and an increase in version number as follows:

Version x.y.z

where:

- x the first digit:
 - 1 presented to TSG for information;
 - 2 presented to TSG for approval;
 - 3 or greater indicates TSG approved document under change control.
- y the second digit is incremented for all changes of substance, i.e. technical enhancements, corrections, updates, etc.
- z the third digit is incremented when editorial only changes have been incorporated in the document.

Introduction

TS 23.204 [5] specifies how to deliver SMS over generic 3GPP IP access, where the Short Message (SM) is entirely encapsulated in the SIP based messages so that the traditional SM not only can be delivered in CS, but also in IMS over different IP-CANs. However, the interworking between the Short Message and the Instant Messaging has not been defined yet, which prohibits the message interworking between the traditional SMS terminals and the non-SMS capable terminals.

As a result, there is an interest for supporting service level interworking for instance between Short Message (SM) and existing Instant Messaging (IM) services, which enables the communication between SMS terminals and the terminals that do not support the SMS, such as pure SIP terminals. This TR documents alternatives for how to provide such service level interworking.

1 Scope

This document contains the results of the study into the architectural requirements and comes up with the solution of the service level interworking for the Short Message service as defined in the TS 23.040 [6] and Instant Messaging service as defined in OMA-TS-SIMPLE_IM-V1_20070816-C [8]. Considerations include overall requirements, architectural requirements, evaluation of potential architectural solutions and alternative architectures.

The objective is to identify an architectural solution that allows completely service level interworking between SMS and SIMPLE IM without degrading existing services, under the service requirements defined in the TS 22.340 [2] and TS 22.105 [3]. In addition, how to charge for the interworked services shall be considered in this study as well.

2 References

The following documents contain provisions which, through reference in this text, constitute provisions of the present document.

- References are either specific (identified by date of publication, edition number, version number, etc.) or non-specific.
- For a specific reference, subsequent revisions do not apply.
- For a non-specific reference, the latest version applies. In the case of a reference to a 3GPP document (including a GSM document), a non-specific reference implicitly refers to the latest version of that document in the same Release as the present document.

[1]	3GPP TR 21.905: "Vocabulary for 3GPP Specifications".
[2]	3GPP TR 22.340: "IP Multimedia System (IMS) messaging".
[3]	3GPP TS 22.105: "Services and service capabilities".
[4]	3GPP TS 23.228: "IP Multimedia Subsystem (IMS); Stage 2".
[5]	$3\mbox{GPP TR }23.204: "Support of Short Message Service (SMS) over generic 3GPP Internet Protocol (IP) access".$
[6]	3GPP TS 23.040: "Technical realization of the Short Message Service (SMS) Point to Point (PP)".
[7]	3GPP TS 24.011: "Point-to-Po int (PP) Short Message Service (SMS) support on mobile radio interface".
[8]	OMA: "Instant Messaging using SIMPLE", OMA-TS-SIMPLE_IM-V1_0-20070816-C, http://member.openmobilealliance.org/ftp/Public_documents/MWG/IM/Permanent_documents/OMA-TS-SIMPLE_IM-V1_0-20070816-C.zip
[9]	IETF draft, draft-ietf-simple-imdn-06: "Instant Message Disposition Notification", 14 January 2008.
[10]	3GPP TS 24.247: "Messaging service using the IP Multimedia (IM) Core Network (CN) subsystem; Stage 3".
[11]	3GPP TS 24.229: "IP multimedia call control protocol based on Session Initiation Protocol (SIP) and Session Description Protocol (SDP); Stage 3".
[12]	3GPP TS 24.341: "Support of SMS over IP networks; Stage 3".

3 Definitions and abbreviations

3.1 Definitions

For the purposes of the present document, the terms and definitions given in TR 21.905 [1] and the following apply. A term defined in the present document takes precedence over the definition of the same term, if any, in TR 21.905 [1].

IMS origination: origination of an Instant Message by an IMS UE.

IMS termination: termination of an Instant Message by an IMS UE.

SMS origination: origination of a Short Message (including SMS over IP) by an SMS capable UE, as defined in TS 23.040 [6] and TS 23.204 [5].

SMS termination: termination of a Short Message (including SMS over IP) by an SMS capable UE, as defined in TS 23.040 [6] and TS 23.204 [5].

SIMPLE IM service: the Instant Messaging Service as defined in the OMA-TS-SIMPLE_IM-V1_0-20070816-C [8].

SMS: the Short Message Service as defined in the TS 23.040 [6]

SMS IP MESSAGE: an immediate message as defined in TS 23.228 [4], which encapsulates a SM in its text body.

Instant Message: an Instant Message as defined in the OMA-TS-SIMPLE_IM-V1_0-20070816-C [8] and TS 24.247 [10].

SMS IP UE: a UE which supports SMSIP MESSAGE.

3.2 Abbreviations

For the purposes of the present document, the following abbreviations apply:

(void)

4 Overall requirements

This document should consider in priority (but not being limited to) the following aspects:

- providing a consistent service experience to the user when service-level interworking takes place;
- providing requirements for suitable security mechanisms for interworked messages, for instance stop certain message from being interworked;
- providing the service-level interworking authorisation;
- avoiding overlap with OMA;
- providing the appropriate mechanisms to apply charging principles for interworking;
- considering the interaction with existing functionality specified in TS 23.040 [6].

NOTE: For ensuring the integrity of the response messages from the IM UE, it is strongly recommended that in networks where the IP-SM-GW is deployed, no intermediate nodes modify or terminate the message between the IP-SM-GW and the terminating IM UE. If intermediate nodes are deployed, they can send response messages that do not reflect the final response from the IM UE. Final responses from the IM UE are necessary to ensure correct charging and delivery reports on the SMS side.

5 Scenarios for service-level interworking

5.1 General

The following clauses describe the use cases and the scenarios to consider in this TR. Note that other scenarios could be added when identified.

5.2 Capability of the UE

The set of supported capabilities of the UE in the terminated network is important for the network entity to decide whether service level interworking is needed. From the terminal's perspective, supporting Instant Message implies that the UE is an IM Client. At least, it requires the UE to support IM feature-tag '+g.oma.sip-im' and IM DN procedure for message delivery report. However, for SM over CS/PS domain, it requires UE to support SMS protocol stack, for SM over IP as defined in TS 23.204 [5], it requires the UE to support both the SMS protocol stack and IMS SIP MESSAGE. As a result, different sets of UE capabilities should be considered when identifying the interworking scenarios.

Category one: IMS registered UE only supporting Instant Message

This type of UE registers to the Instant Message service as well as the IMS service. However, it only supports the Instant Message format. In other words, service level interworking needs to be done when Short Message is received from the other side based on the capability of the UE. Otherwise, the UE is not able to resolve the message format.

Category two: IMS registered UE only supporting SMSIP MESSAGE

This type of UE registers to the IMS service but does not register to Instant Message service and it supports the SMSIP MESSAGE format. In this case, when it is sent an Instant Message service level interworking is needed.

Category three: IMS registered UE supporting both SMSIP MESSAGE and Instant Message

This type of UE registers to the Instant Message service as well as the IMS service and it supports the SMSIP MESSAGE and Instant Message simultaneous. This means that when it is sent a Short Message, no message format translation is needed, and it is only necessary to encapsulate the Short Message in the text body of the SIP MESSAGE. Optionally, service level interworking can be also performed based on the preference and the subscription of the user for this type of UE.

Category four: SM UE over PS/CS

This type describes legacy UEs that only support short messages. When it is sent a pure IM, service level interworking is required, otherwise, the UE is not able to resolve the message format.

5.3 Use cases

5.3.1 IM user with non SMS capable UE receives short message from an SMS user

An IMS registered user with SIMPLE IM service receives an SMS message formatted via service-level interworking to an Instant Message.

5.3.2 IM user with non SMS capable UE sends an Instant Message to an SMS user

An IMS registered user with SIMPLE IM service sends an Instant Message to an SMS recipient formatted via service-level interworking to an SMS message.

5.3.3 IMS user with delivery preferences/operator policy set to SMS for receiving messages

An Instant Message is received for an IMS subscriber where the subscriber has set terminating user preferences to deliver all Instant Messages via SMS (e.g. because the user is not available in IMS) or operator policy determines that this Instant Message shall be delivered as short message.

5.3.4 Concatenated SMS messages delivered as an IM large message

An IMS registered user with OMA IM service receives an SMS via service-level interworking to MSRP (needed for large SMS's).

5.3.5 IM large message delivered as concatenated SMS messages

An IMS registered user with OMA IM service sends a message via MSRP (needed for a large message) where the recipient is not an IMS user.

5.3.6 IM user with delivery preferences set to SMS for large messages

An IMS registered user with OMA IM service sends a message via MSRP where the recipient is an IMS user but the user has set terminating user preferences to deliver all Instant Messages received via MSRP via SMS (perhaps because the user is not available in IMS).

5.3.7 Prevention from being interworked

Some SMS messages are prevented from being interworked to IMS based on the specific SMS service (e.g., a priority SMS, OTA SMS, etc.).

5.3.8 IM user sends an Instant Message to an SMSIP UE

An IM user sends an Instant Message to an SMSIP UE via the service level interworking to an encapsulated SIP MESSAGE.

5.3.9 SMSIP UE sends an encapsulated Short Message to an IM user with non SMS capable UE

An SMSIP UE sends an encapsulated Short Message to an IM user with non SMS capable UE via the service level interworking to an Instant Message.

5.3.10 IM user sends an Instant Message to a group list including SMS users

An IM user sends an Instant Message to a group list which includes the recipients of the SMS users as well as the IM users.

5.3.11 AS addressed by PSI receives short message from an SMS user

AS addressed by PSI receives an SMS message formatted via service-level interworking to an Instant Message.

5.4 Scenarios

5.4.1 Scenario 1: IMS origination and SMS termination to the SMS UE with the service level interworking in the originating side

A IM UE in itiates an Instant Message and the Instant Message is terminated as a Short Message in the CS or PS domain to a SMS UE.




Figure 5.1: interworking scenario of IMS origination and SMS termination to the SMS UE-1

5.4.2 Scenario 2: IMS origination and SMS termination to the SMS UE with the service level interworking in the terminating side

A IM UE initiates an Instant Message and the Instant Message is terminated as a Short Message in the IMS to a SMS UE.




Figure 5.2: interworking scenario of IMS origination and SMS termination to the SMS UE-2

5.4.3 Scenario 3: SMS origination from the SMS UE and IMS termination

A SMS UE initiates a Short Message over CS or PS domain and the Short Message is terminated as an Instant Message in the IMS to an IM UE.




Figure 5.3: interworking scenario of SMS origination from the SMS UE and IMS termination

5.4.4 Scenario 4: SMSIP UE sends an encapsulated Short Message to an IM user

A SMSIP UE initiates an encapsulated Short Message and the Short Message is terminated as an Instant Message in the IMS to an IM UE.




Figure 5.4: interworking scenario of SMS origination from the SMSIP UE and IMS termination

The encapsulated Short Message is sent from the SMSIP client to the Originating S-CSCF.

The IP-SM-GW on the originating side translates the encapsulated Short Message into a Short Message for delivery to the SM-SC as described in TS 23.204 [5], clause 6.3.

The SM-SC delivers the short message to the IM user according to the procedures in subclause 7.1.1.4.2 (IM user receives short message from an SMS user).

5.4.5 Scenario 5: IMS origination and SMS termination to the SMSIP UE with the service level interworking in the terminating side

A IM UE initiates an Instant Message and the Instant Message is terminated as a SMSIP MESSAGE in the IMS
to a SMSIP UE.




Figure 5.5: Interworking scenario of IMS origination and SMS termination to the SMSIP UE-3

The IM client sends an Instant Message.

The IP-SM-GW on the terminating side translates the Instant Message into a Short Message by performing service level interworking and then delivers the message as a Short Message over IMS.

6 Architectural requirements

The SMS-IM service level interworking architecture shall allow for the following:

- The service level interworking is a value added service which requires service subscription, In addition, it shall also take the operator's policy, if available, into account, e.g. checking on the barring setting of the subscriber to determine whether to provide this interworking or not, so the service authorisation shall be supported before the interworking is executed.
- The service level interworking applies as a fallback only in case the users cannot communicate with each other using their chosen messaging service, subject to user preferences and operator policies. The location of the interworking service can be in the originating network when the sender sends a message that needs to be interworked, and in the terminating network when the message is to be delivered in a format different than the one it was received in.
- The service level interworking shall support interworking between OMA SIMPLE IM service as defined in OMA-TS-SIMPLE_IM-V1_0-20070816-C [8] and Short Message Service, which includes not only the Short message over CS/PS as defined in the TS 23.040 [6] but also the short message over IP as defined in the TS 23.204 [5].
- The service level interworking shall not break existing functionality.

- The service level interworking shall be able to take the capability of the terminating UE into account when possible.
- The service level interworking shall be transparent to the end user.
- The service level interworking shall minimize the impact on the IMS architecture.
- The service level interworking shall not impact existing functionality of the SMS service as described in TS 23.040[6] or of the SIMPLE IM service enabler as described in OMA-TS-SIMPLE_IM-V1_0-20070816-C [8]. Existing security mechanisms for both the SIMPLE IM service and the SMS service shall be reused.
- The service level interworking shall minimize the impact on existing functionality of the SIP based messaging service as described in TS 23.204 [5]. Existing security mechanisms for SIP based messaging service shall be reused.
- Delivery to offline subscribers shall be supported in the receiving system.
- The interworking function shall be aware if the message should be interworked or not, e.g., s pecific types of SMS messages such as an over the air configuration message, shall not be interworked, but shall be instead transported as an SMS message via IMS, CS or PS.
- If an SMS user requests an SMS status report that the message was delivered to the recipient and the SM is interworked to IM on the originating side, then an SMS status report shall be generated by the interworking function when the message is delivered as an Instant Message.
- If an IMS user requests a notification that the message was delivered to the recipient, an SMS status report shall be generated when the message is delivered to the SMS user's client.
- The interworking function shall generate the appropriate charging-related information and provide the appropriate online charging mechanism (if it is applied for the SMS and/or SIMPLE IM services) for the interworking services.
- Functionality is required to be able to select the domain for message delivery between IMS and CS/PS, and to have the message delivered to the selected domain.
- Functionality is required to determine whether to transform the message format or not, and to performed the transformation of the message format when determined.
- The interworking functionality shall be executed in the following cases:
 - The sender is an IM user and the recipient is an SMS user, e.g., the recipient is not routeable in IMS.
 - The operator policy on the originating side has been set to send the Instant Messages via SMS.
 - The user preferences and/or the operator policy of the recipient have been set to receive the incoming Instant Messages via SMS.
 - The sender is an SMS user and the recipient is an IM user.

7 Architecture alternatives

Editor's Note: This clause will describe and evaluate detailed reference architectures, including network elements, interfaces and reference points, suitable to provide SMS-IM service level interworking.

7.1 Alternative 1

7.1.1 Architectural details

7.1.1.1 Reference architecture

The overall architecture for translation between SMS and IM Messaging is the same as the architecture for SMS over IP as specified in TS 23.204 [5].




Figure 7.1.1.1: Architecture for providing Service Level (SMS and IM) Inter-working

7.1.1.2 Reference points

The same reference points as specified in TS 23.204 [5] are employed to support protocol interworking and translation between SMS and IM Messaging.

7.1.1.3 Functional entities for IP-SM-GW

The IP-SM-GW shall perform all the functions as described in TS 23.204 [5].

The IP-SM-GW shall select the domain for message delivery between IMS and CS/PS, and shall have the message delivered to the selected domain.

The IP-SM-GW shall determine whether to transform the message format or not, and shall perform the transformation of the message format when determined.

The IP-SM-GW shall either use the SC address retrieved as part of the subscriber data from the HSS at registration or as provisioned by configuration when transforming the Instant Message into Short Message.

In addition, the IP-SM-GW shall perform the authorization for service level interworking.

7.1.1.4 Procedures

7.1.1.4.1 IM capable UE sends an Instant Message to an SMS user




Figure 7.1.1.4.1: Successful MO Instant Message to SMS procedure

- 1) The UE registers to S-CSCF according the IMS registration procedure. Note that I-CSCF and P-CSCF are not shown in this figure.
- 2) UE submits the Instant Message to the S-CSCF using an appropriate SIP method.
- 3) S-CSCF forwards the Instant Message to IP-SM-GW based on stored iFC.

NOTE 1: Subscribers with no subscription for service level interworking will be provided with the relevant iFCs.

- 4) The IP-SM-GW shall decide whether to perform service level interworking depending on SIP request header (e.g., R-URI), operator policy, when the Instant Message is not routable in the IMS. If IP-SM-GW decided to perform service level interworking, the IP-SM-GW performs service authorization based on the stored subscriber data retrieved from the HLR/HSS at the time of the third party registration procedure as specified in TS 23.204 [5]. The IP-SM-GW shall check whether the originating subscriber is authorised to use the interworking service. If the result of service authorization is negative, the IP-SM-GW shall not forward the message, and shall return the appropriate error information to the UE in a failure report. Otherwise, the IP-SM-GW shall use the SC Address in the subscriber data retrieved from the HSS at registration or provisioned by configuration and translates the Instant Message to the SMS (SMS-SUBMIT) carrying SC Address, then forwards it towards SC (SC Address) via the SMS-IWMSC (as described in TS 23.040 [6]). If the size of the content of the Instant Message is larger than the size of the content that one Short Message could transfer, the IP-SM-GW shall split the content of the Instant Message into several parts, translate them to concatenated Short Messages, and forward the concatenated Short Messages to SC as described in TS 23.040 [6].
- 5) If service authorization is successful, the IP-SM-GW acknowledges the Instant Message.
- 6) Instant Message acknowledgement is forwarded by S-CSCF to UE.
- NOTE 2: Steps 5 and 6 can occur anytime after the subscriber authorization check has been performed by the IP-SM-GW.
- 7) The SMS-IWMSC forwards the SMS message (SMS-SUBMIT) to the SC (see TS 23.040 [6]).
- 8) SC sends SUBMIT-REPORT to SMS-IWMSC (see TS 23.040 [6]).
- 9) SMS-IWMSC sends SUBMIT-REPORT to IP-SM-GW (see TS 23.040 [6]).
- 10) IP-SM-GW translates the received SUBMIT-REPORT to an appropriate IMS Message, and forwards it to the S-CSCF. If the IP-SM-GW sends concatenated Short Messages to SC in step 4, the IP-SM-GW should wait the last SUBMIT-REPORT, and translate the last SUBMIT-REPORT to an appropriate IMS Message, and forward it to the S-CSCF.
- 11) S-CSCF sends the translated Instant Message to the UE.
- 12) UE acknowledges the translated Instant Message.
- 13) Acknowledgement of the translated Instant Message is forwarded by S-CSCF to IP-SM-GW.
- NOTE 3: As mentioned in Figure 7.2.1.4.1 (similar flow for Alternative 2), flow might end in step 9, means Steps 10 to 13 occur only if the IM user requested a delivery report in the message sent in step 2.

7.1.1.4.2 IM user receives short message from an SMS user

An IMS registered user with SIMPLE IM service receives a SM message formatted via service-level interworking to an Instant Message.




Figure 7.1.1.4.2: Successful SM to Instant Message delivery procedure, including Successful Delivery Report

- 1) The UE registers to the S-CSCF according to the IMS registration procedure. Note that the I-CSCF and P-CSCF are not shown in this figure.
- 2) The SMS-SC forwards an SM to the SMS-GMSC.
- NOTE 1: It is assumed that the message is destined to UE with a Tel-URI, otherwise HLR/HSS will not be able to resolve the none-msisdn address.
- 3a) The SMS-GMSC interrogates the HSS to retrieve routeing information. Based on the pre-configured IP-SM-GW address for the user, the HSS forwards the request to the corresponding IP-SM-GW
- 3b) The HLR/HSS returns the IMSI and the address(es) of the current MSC and/or SGSN to the IP-SM-GW for delivery of the SM in CS/PS domain.
- 3c) The IP-SM-GW creates a Correlation Identifier as per TS 23.040 [6], which associates the Routeing Info retrieval with the subsequent ForwardSM messages(s), and stores this along with the IMSI of the receiving subscriber. The IP-SM-GW returns to the SMS-GMSC the address of itself, along with the Correlation Identifier in the IMSI field, as routeing information. Alternatively, the IP-SM-GW may return the address(es) of the current MSC and/or SGSN, in which case, the subsequent procedure to forward the message is the same as defined in TS 23.040 [6].
- 4) The SMS-GMSC delivers the short message to the IP-SM-GW in the same manner that it delivers the short message to an MSC or SGSN, including the Correlation Identifier received from the IP-SM-GW, in place of the IMSI.

- 5) The IP-SM-GW checks whether the recipient is authorized for the interworking service.
- NOTE 2: The IP-SM-GW will determine whether the transport level interworking or the service level interworking is to be preformed based on the users' subscription and authorisation, and on the UE capability as indicated during IMS registration. If the user has subscribed to both services, is authorised for both and the UE has indicated its capability to receive both encapsulated Short Messages and Instant messages, the priority between the transport-level interworking and the service-level interworking is based on operator policy and user preferences. If the authorization fails for both services, an error is returned.
- 6) If the user is authorized to the service level interworking, the IP-SM-GW converts the SM to an Instant Message. It sends the IM using the appropriate SIP method towards the S-CSCF.
- 7) The S-CSCF forwards the Message to the UE.
- 8) The UE sends a response back to the S-CSCF.
- 9) The S-CSCF sends the response to the IP-SM-GW.
- 10) The IP-SM-GW acknowledges the ForwardSM to the SMS-GMSC.
- 11) The SMS-GMSC may send an SM delivery report status to the HLR/HSS for either of the following cases:
 - setting of the Message Waiting flags when the ForwardSM was unsuccessful;
 - clearing of the Message Waiting flags in HLR/HSS when the ForwardSM was successful, but had previously failed.

NOTE 3: See TS 23.040 [6] for a full explanation of when the Message Waiting flags are set and unset.

12) The SMS-GMSC sends a delivery report (status) to the SMS-SC.

7.1.1.4.3 Concatenated SM messages delivered as an IM large message

An IMS registered user with IM service receives a concatenated short message delivered as two or more short messages. The received concatenated short message may or may not exceed the maximum payload size of an Instant Message.




Figure 7.1.1.4.3: Concatenated SMS messages delivered as an IM large message

- 1) The UE registers to the S-CSCF according to the IMS registration procedure. Note that the I-CSCF and P-CSCF are not shown in this figure.
- 2) The SMS-SC forwards an SMS SM that is part of a concatenation of two or more SMs to the SMS-GMSC.
- 3a) The SMS-GMSC interrogates the HSS to retrieve routeing information. Based on the pre-configured IP-SM-GW address for the user, the HSS forwards the request to the corresponding IP-SM-GW.
- 3b) The HLR/HSS returns the IMSI and the address(es) of the current MSC and/or SGSN to the IP-SM-GW for delivery of the SMS SM in CS/PS domain.
- 3c) The IP-SM-GW creates a Correlation Identifier as per TS 23.040 [6], which associates the Routeing Info retrieval with the subsequent ForwardSM messages(s), and stores this along with the IMSI of the receiving subscriber. The IP-SM-GW returns to the SMS-GMSC the address of itself, along with the Correlation Identifier in the IMSI field, as routeing information. Alternatively, the IP-SM-GW may return the address(es) of the current MSC and/or SGSN, in which case, the subsequent procedure to forward the message is the same as defined in TS 23.040 [6].
- 4) The SMS-GMSC delivers the short message to the IP-SM-GW in the same manner that it delivers the short message to an MSC or SGSN, including the Correlation Identifier received from the IP-SM-GW, in place of the IMSI.

- 5) The IP-SM-GW checks whether the recipient is authorized for the interworking service. If the user is authorized to the service level interworking, the IP-SM-GW recognizes that the received message is part of a concatenated SMS message and stores the received message.
- NOTE 1: The IP-SM-GW will determine whether the transport level interworking or the service level interworking is to be preformed based on the users' subscription and authorisation, and on the UE capability as indicated during IMS registration. If the user has subscribed to both services, is authorised for both and the UE has indicated its capability to receive both encapsulated Short Messages and Instant messages, the priority between the transport-level interworking and the service-level interworking is based on operator policy and user preferences. If the authorization fails for both services, an error is returned.
- NOTE 2: The IP-SM-GW needs to have access to a persistance storage in order to aggregate all the SM parts.
- 6) The IP-SM-GW acknowledges the ForwardSM to the SMS-GMSC.
- 7) The SMS-GMSC may send an SM delivery report status to the HLR/HSS for either of the following cases:
 - setting of the Message Waiting flags when the ForwardSM was unsuccessful;
 - clearing of the Message Waiting flags in HLR/HSS when the ForwardSM was successful, but had previously failed
- 8) The SMS-GMSC sends a delivery report (status) to the SMS-SC.
- NOTE 3: steps 7 and 8 need to be verified.
- 9) The SMS-SC forwards the next SMS SM that is part of a concatenation of two or more SMs to the SMS-GMSC. If this is not the last SM of the concatenation, then processing continues at step 4.
- 10) If this is the last SM of the concatenation then the SMS-GMSC delivers the short message to the IP-SM-GW in the same manner that it delivers the short message to an MSC or SGSN, including the Correlation Identifier received from the IP-SM-GW, in place of the IMSI.
- 11) The IP-SM-GW checks whether the recipient is authorized for the interworking service. If the user is authorized to the service level interworking, the IP-SM-GW recognizes that the received message is part of a concatenated SMS message and stores the received message.
- NOTE 4: The same interworking service will be authorized as selected in step 5 at this stage in order to have all the concatenated messages sent using the same message format.
- 12-13) Once all the segments have been received, the IP-SM-GW establishes an MSRP session with the recipient's UE to deliver the message. The session invitation is sent to the recipient UE.
- NOTE 5: As a matter of implementation efficiency, the IP-SM-GW may initiate the connection towards the recipient after receiving the first ForwardSM and passing a service authorization check. This may help prevent timeouts at the SMS-GMSC (while it waits for the final ForwardSM Ack) but may also result in unnessary session initiation signalling if there is a failure in a service check for subsequently received SMs.
- NOTE 6: The IP-SM-GW needs to have access to a persistance storage in order to aggregate all the SM parts.
- 14) The IP-SM-GW delivers the message in one or more MSRP SEND requests to the recipient UE
- 15) -16) The IP-SM-GW closes the session after message delivery is complete.
- 17) The IP-SM-GW acknowledges the ForwardSM to the SMS-GMSC.
- 18) The SMS-GMSC may send an SM delivery report status to the HLR/HSS for either of the following cases:
 - setting of the Message Waiting flags when the ForwardSM was unsuccessful;
 - clearing of the Message Waiting flags in HLR/HSS when the ForwardSM was successful, but had previously failed.
- NOTE 7: See TS 23.040 [6] for a full explanation of when the Message Waiting flags are set and unset.
- 19) The SMS-GMSC sends a delivery report (status) to the SMS-SC.

7.1.1.4.4 Status Report procedure for Instant Message to SMS message interworking




Figure 7.1.1.4.4: Status report procedure for Instant Message to SMS interworking

- 1) The UE has successfully received the short message, and the original message in the IMS domain requested a Disposition notification.
- NOTE 1: A Disposition Notification can be requested in the message sent by the UE in step 1 as described in IETF IMDN draft-ietf-simple-imdn-06 [9]. If the requested Disposition Notification by the IM user is a request for a read notification, the IP-SM-GW ignores the request.
- 2) The SMS-SC sends a status report to the SMS-GMSC. NOTE: The status report will, from the SMS-GMSC's point of view be treated as any MT SMS delivery.
- NOTE 2: The status report is an optional message.
- 3a) The SMS-GMSC interrogates the HSS to retrieve routeing information. Based on the pre-configured IP-SM-GW address for the user, the HSS forwards the request to the corresponding IP-SM-GW.
- 3b) The HLR/HSS returns the IMSI and the address(es) of the current MSC and/or SGSN to the IP-SM-GW for delivery of the SMS SM in CS/PS domain.
- 3c) The IP-SM-GW creates a Correlation Identifier as per TS 23.040 [6], which associates the Routeing Info retrieval with the subsequent ForwardSM messages(s), and stores this along with the IMSI of the receiving subscriber. The IP-SM-GW returns to the SMS-GMSC the address of itself, along with the Correlation Identifier in the IMSI field, as routeing information. Alternatively, the IP-SM-GW may return the address(es) of the current MSC and/or SGSN, in which case, the subsequent procedure to forward the message is the same as defined in TS 23.040 [6].
- 4) The SMS-GMSC sends the status report to the IP-SM-GW.
- NOTE 3: Steps 5 to 11 only occur if the original IM requested a delivery notification in the Disposition Notification.

- 5) The IP-SM-GW translates and maps the SMS status report into an IM message carrying a delivery notification as described in the IETF IMDN draft-ietf-simple-imdn-06 [9]. The IP-SM-GW should keep the message id for a message for which IMDN was requested so it can send the message id to the UE in the IMDN.
- 6-7) The IP-SM-GW sends a delivery notification to the S-CSCF, which sends it to the UE.
- 8-9) The UE acknowledges receipt of the delivery notification to the S-CSCF. The S-CSCF sends the acknowledgment to the IP-SM-GW.
- 10) The IP-SM-GW sends a Forward SM Ack to the SMS-GMSC.
- 11) The SMS-GMSC sends an acknowledgement back to the SMS-SC.

7.1.1.4.5 IMS registered user with delivery preferences/operator policy set to SMS for receiving short messages

In this case, the delivery procedures are the same as described in TS 23.040 [6], clause 10.1.

7.1.1.4.6 Delivery to unregistered subscriber

When a short message is received in the IP-SM-GW for delivery to an IM user, the IP-SM-GW shall verify the registration status of the IM user. If the user is not registered in IMS, the delivery of the Instant Message will not be allowed, to prevent the message from being deferred in the IM system, and according to operator policy and user preferences, either the message is sent over CS/PS as described in TS 23.204 [5], or an error indication is sent back to the SM-SC. In that case, when the IM user registers at a later time, this information is sent to the SM-SC and the delivery is attempted at that time.




Figure 7.1.1.4.6: Delivery procedure

- 1) A Short Message is destined to be delivered to an IM user as described in clause 7.1.1.4.2 steps 2 to 4.
- 2) The IP-SM-GW checks the registration status of the IM user. This user is currently not registered for the SMS-IM interworking service and the IP-SM-GW has determined that the message is not to be delivered over CS/PS, so the IP-SM-GW sends an SMS-DELIVERY-REPORT with an appropriate error code to the SMS-GMSC.
- 3) The SMS-GMSC forwards the SMS-DELIVER Y-REPORT to the SM-SC.

- 4) The SMS-GMSC sends a SM Delivery Report Status to the HSS, indicating that the message failed to be sent by the IP-SM-GW. The HSS records the corresponding MWD, i.e. the SM-SC address which stores the undelivered message and the failure reason which indicates that the message failed to be sent by IP-SM-GW due to the UE not being available.
- 5) At any time after the unsuccessful SMS MT delivery procedure, the UE may register in IMS again, the UE is registered at the S-CSCF according to the IMS registration procedures.
- 6) After the IMS registration is finished, the HLR/HSS checks the user's MWD, and if it is not Null, the HLR/HSS initiates an alert service centre message to the SM-SC (through the SMS-IWMSC) according to the stored MWD in step 4.
- 7) Upon receipt of the alert service centre message, the SM-SC re-attempts to send the stored short message as described in the clause 7.1.1.4.2.

7.1.1.4.7 AS addressed by PSI receives short message from an SMS user

The SMS-SC forwards a Short Message to the IP-SM-GW, as described in step 2 to 4 of 7.1.1.4.2. The IP-SM-GW checks if the recipient is an AS addressed by a PSI. If the recipient is an AS addressed by a PSI, the IP-SM-GW sends the Message to I-CSCF. I-CSCF routes the Message to the AS addressed by the PSI according to normal PSI routeing procedures. The AS addressed by the PSI sends a response back to the I-CSCF. The I-CSCF forwards the response to the IP-SM-GW.

7.1.1.4.8 IM user sends an Instant Message to an SMSIP UE

An IMS registered user with SIMPLE IM service sends an Instant Message via service-level interworking to an SMSIP MESSAGE to an SMSIP UE, which did not indicate support for SIMPLE IM when registering to IMS.

NOTE 1: Based upon user subscription and depending on network deployment, other Application Servers could be processing the incoming Instant Message before the IP-SM-GW. The behaviour of the IM AS is described in OMA-TS-SIMPLE_IM-V1_0-20070816-C [8] and TS 24.247 [10].




Figure 7.1.1.4.8: Successful MT Instant Message to SMSIP MESSAGE procedure

1) IM UE sends an Instant Message to the S-CSCF#1.

- 2) The S-CSCF#1 forwards the Instant Message to the S-CSCF#2.
- 3) The S-CSCF forwards the Instant Message to the IP-SM-GW based on iFC.
- 4) Based on user subscription and authorisation for service-level interworking, on operator policy and user preferences, and on UE capability indicated during IMS registration, the IP-SM-GW shall decide whether to perform the service-level interworking. If the user is subscribed and authorised for transport-level interworking, and based on UE capability indicated during IMS registration, and on operator policy and user preferences, the message may be delivered as an encapsulated Short Message to the UE over IMS. Otherwise, the Short Message is delivered over CS/PS, as described in clause 7.1.1.4.10. If the incoming Instant Message requested a delivery notification, the IP-SM-GW includes the Status Report Request described in TS 23.040 [6] in the outgoing SMS or SMSIP MESSAGE.
- NOTE 2: If a delivery notification was requested in the message sent by the UE in step 1 as described in IETF IMDN draft-ietf-simple-imdn-06 [9], the procedure for delivery report described in clause 7.1.1.4.9 applies. Otherwise IP-SM-GW will just acknowledge, at the SIP level, the Delivery report received from the SMSIP UE.
- 5) The IP-SM-GW forwards the SMSIP MESSAGE to the S-CSCF#2.
- 6) The S-CSCF#2 forwards the SMSIP MESSAGE to the SMSIP UE.
- 7) The SMSIP UE acknowledges the translated SMSIP MESSAGE.
- 8) Acknowledgement of the translated SMSIP MESSAGE is forwarded by the S-CSCF to the IP-SM-GW.
- 9-11) Acknowledgement of the translated SMSIP MESSAGE is forwarded by the IP-SM-GW to the originating IM UE.

7.1.1.4.9 Delivery report for an Instant Message delivered as SMSIP MESSAGE

This procedure follows the procedure described in 7.1.1.4.8, when the original Instant Message included a delivery notification request.




Figure 7.1.1.4.9: Delivery report after a successful Instant Message to SMSIP Message procedure

NOTE: An SMSIP MESSAGE has been sent successfully according to the procedure described in clause 7.1.1.4.8 before the procedure below can be performed.

- 1-2) The SMSIP UE has received the short message as described in clause 7.1.1.4.8 and sends a SMS-DELIVER Y-REPORT to the IP-SM-GW via the S-CSCF.
- 3-4) The IP-SM-GW acknowledges, at the SIP level, the SMS-DELIVERY-REPORT to the SMSIP UE via the S-CSCF.
- 5-7) The IP-SM-GW sends a Delivery Notification to the IM UE.
- 8-10) The IM UE acknowledges the reception of the Delivery Notification.

7.1.1.4.10 IM capable UE sends an IM to an SMS user with Interworking in the terminating side

The IM capable UE registers to S-CSCF according to the IMS registration procedure. Note that the I-CSCF and P-CSCF are not shown in this figure.




Figure 7.1.1.4.10: Successful IM originating to SMS procedure with Interworking in the Terminating Side

- UE submits an Instant Message, destined to another IM user in another IMS domain, using an appropriate SIP method.
- 2) The S-CSCF resolves the destination domain and routes the message towards the S-CSCF in the terminating network ("Terminating S-CSCF").
- 3) The terminating S-CSCF forwards the Instant Message to the IM AS ("Terminating IM AS") based on stored iFC.
- 4) The terminating IM AS invokes terminating IM services as applicable for the destination IM user.
- 5) The IM AS can forward the Instant Message back to the terminating S-CSCF, e.g. the terminating IM user is offline.
- 6) The terminating S-CSCF forwards the Instant Message to the IP-SM-GW, e.g. based on stored iFC.
- 7) If the user is authorized, the IP-SM-GW performs service-level interworking by converting the IM to SMS. The IP-SM-GW shall obtain the routeing information for the UE from the HLR/HSS and deliver the message to the UE.
- 8) The IP-SM-GW obtains the routeing information for the destination UE from the HLR/HSS.

- 9) The IP-SM-GW sends the MT Forward SM message to the target MSC.
- 10) The MSC sends the Short Message to the UE.
- 11) The UE acknowledges the receipt of the Short Message.
- 12) The MSC sends Forward SM Ack to the IP-SM-GW.
- 13) The IP-SM-GW sends OK response to the terminating S-CSCF.
- 14) The S-CSCF forwards the OK to the terminating IM AS.
- 15) The terminating IM AS forwards the OK response back to the terminating S-CSCF.
- 16) The terminating S-CSCF forwards the OK back towards the originating S-CSCF.
- 17) The originating S-CSCF forwards the OK to the originating UE.

7.1.2 Impact

7.1.3 Assessment

7.2 Alternative 2

7.2.1 Architectural details

7.2.1.1 Reference architecture




Figure 7.2.1.1: SMS-IM service-level interworking architecture

7.2.1.2 Reference points

The same reference points as specified in TS 23.204 [5] are employed to support protocol interworking and translation between SMS and IM Messaging.

One new reference point My is proposed in this architecture to allow routeing to the IP-SM-GW in the originating network.

NOTE: The ISC interface is used only in the terminating network.

7.2.1.2.1 My Reference Point

This reference point allows the Breakout Gateway Control Function (BGCF) to forward the session signalling to the IP-SM-GW for the purpose of interworking between the IM and SMS services in the originating network.

The My reference point is based on external specifications, i.e. SIP.

7.2.1.3 Functional Entities IP-SM-GW

The IP-SM-GW shall perform the subscription checking, the authorization for service level interworking, protocol interworking and the translation between SMS and IMS messaging. The IP-SM-GW includes the functionality described in TS 23.204 [5].

7.2.1.4 Procedures

7.2.1.4.1 IM user sends an Instant Message to an SMS user




Figure 7.2.1.4.1: Successful MO Instant Message to SMS procedure

- 1) UE submits the Instant Message to the S-CSCF using the appropriate SIP method. Initial filter criteria is checked in the S-CSCF for originating services and routeing towards any application servers takes place. The message is addressed using a TEL URI for the recipient.
- 2) After originating services have been executed, the S-CSCF processes the Instant Message according to procedures in IMS and since the Request-URI contains a TEL-URI the S-CSCF performs a database lookup to find the corresponding SIP URI. If no SIP URI is found, the S-CSCF forwards the message to the BGCF as described in TS 24.229 [11], clause 5.4.3.2.
- 3) The BGCF makes the routeing decision depending on SIP request method or any other information the BGCF may have indicating where to route a particular TEL URI. In this case, because it is MESSAGE message, it is routed to the IP-SM-GW.

NOTE: A new interface is needed between the BGCF and the IP-SM-GW.

4) Upon receipt of the Instant Message, the IP-SM-GW performs service authorization and determines that the message is destined to an SMS recipient.

- 5) Message accepted information is forwarded by the IP-SM-GW towards the UE. If the result of service authorization is negative, the IP-SM-GW shall return the appropriate error response back to the UE; otherwise a successful response is sent back.
- 6-7) The response is forwarded back to the UE.
- 8) When service is authorized, the IP-SM-GW creates the SMS message from the Instant Message and forwards it towards the SMS-IWMSC using standard MAP signalling (as described in TS 23.040 [6]).
- 9) The SMS-IWMSC forwards the SMS message to the SM-SC (see TS 23.040 [6]).
- 10) The SM-SC sends submit report to the SMS-IWMSC (see TS 23.040 [6]).
- 11) The SMS-IWMSC sends submit report to the IP-SM-GW (see TS 23.040 [6]).

Steps 12 to 17 occur only if the IM user requested a failure delivery report in the message sent in step 2, and only if the submit report was actually a failure report. For a delivery report (successful or failure) sent as a result of a status report, see the flow in clause 7.1.1.4.4.

Editor's Note: Ongoing work in IETF will allow an IM user to request delivery reports (draft-ietf-simple-imdn-06.txt [9]).

- 12) If the submit report was actually a failure report, the IP-SM-GW maps the submit report to a failure delivery report and sends it to the S-CSCF, using a service level mapping of the status information in the submit report to a failure delivery report.
- 13-14) S-CSCF sends the report to the UE.
- 15) The UE acknowledges the report.
- 16-17) Acknowledgement of the report is forwarded by S-CSCF to IP-SM-GW.

7.2.1.4.2 IM user receives short message from an SMS user

This procedure is identical to the procedure described in clause 7.1.1.4.2.

7.2.1.4.3 Concatenated SM messages delivered as an IM large message

This procedure is identical to the procedure described in clause 7.1.1.4.3.

7.2.1.4.4 Status Report procedure for Instant Message to SMS message interworking

This procedure is identical to the procedure described in clause 7.1.1.4.4.

7.2.1.4.5 IMS registered user with delivery preferences/operator policy set to SMS for receiving short messages

This procedure is identical to the procedure described in clause 7.1.1.4.5.

7.2.1.4.6 Delivery to unregistered subscriber

This procedure is identical to the procedure described in clause 7.1.1.4.6. Upon receipt of the alert service centre message, the SM-SC re-attempts to send the stored short message as described in the clause 6.4.

7.2.1.4.7 AS addressed by PSI receives short message from an SMS user

This procedure is identical to the procedure described in clause 7.1.1.4.7.

8 Conclusion

It has been identified that the two alternative architectures for the service-level interworking are identical in the terminating cases, and are only differing in the originating case (clauses 7.1.1.4.1 and 7.2.1.4.1): architecture alternative 1 is using iFCs to route the Instant Messages to the IP-SM-GW, while architecture alternative 2 is going through the BGCF in order to reach the IP-SM-GW.

It is concluded to include architecture alternative 1 in the normative part of TS 23.204 [5].

The architecture and flows have been transferred to TS 23.204 [5] and this Technical Report will not be updated anymore. For an accurate and up-to-date description of service-level interworking, please refer to TS 23.204 [5].

Annex A: IM user sends an Instant Message to a group list including SMS users




Figure A.1: IM user sends an Instant Message to a group list including SMS users

- 1) The UE registers to S-CSCF according the IMS registration procedure. Note that I-CSCF and P-CSCF are not shown in this figure.
- 2) UE generates Instant Message which includes group information, e.g., Group identifier in the R-URI and/or recipient list in the body of the Instant Message. UE submits the Instant Message to the S-CSCF using an appropriate SIP method.
- 3) Based on the stored iFC, S-CSCF forwards the Instant Message to an AS in charge of the group delivery, e.g., the controlling function server defined in OMA-TS-SIMPLE_IM-V1_0-20070816-C [8].

- 4) The group delivery AS replicates per Instant Message for per recipient according to the group information it obtains acting as a B2BUA. See detail in OMA-TS-SIMPLE IM-V1 0-20070816-C [8].
- 5) The group delivery AS sends the generated multiple Instant Messages to S-CSCF (e.g., the Instant Messages can be delivered as what the list server does defined in the TS 24.247 [10]).
- 6) The S-CSCF forwards the Instant Messages to the IP-SM-GW based on the stored iFC.
- 7) The IP-SM-GW shall decide whether to perform service level interworking depending on SIP request header (e.g., R-URI), operator policy, when the Instant Message is not routable in the IMS. If IP-SM-GW decided to perform service level interworking, the IP-SM-GW performs service authorization based on the stored subscriber data as described in the clause XX. The IP-SM-GW shall check whether the originating subscriber is authorised to use the interworking service. If the result of service authorization is negative, the IP-SM-GW shall not forward the message, and shall return the appropriate error information to the UE in a failure report. Otherwise, the IP-SM-GW shall translate the IMS message to the SMS (SMS-SUBMIT) and forwards it towards SC (SC Address) via the SMS-IWMSC (as described in TS 23.040 [6]).
- 8) If service authorization is successful, the IP-SM-GW acknowledges the Instant Messages.
- 9-11) Instant Message acknowledgement is forwarded by S-CSCF to UE.
- 12) The SMS-IWMSC forwards the SMS messages (SMS-SUBMIT) to the SC (see TS 23.040 [6]).
- 13) SC sends multiple SUBMIT-REPORTs to SMS-IWMSC (see TS 23.040 [6]).
- 14) SMS-IWMSC sends the SUBMIT-REPORTs to IP-SM-GW (see TS 23.040 [6]).
- 15) IP-SM-GW translates the received SUBMIT-REPORTs to appropriate IMS delivery notifications defined in draft-ietf-simple-imdn-06.txt [9], and forwards the IMS delivery notifications to the S-CSCF.
- 16) The S-CSCF forwards the IMS delivery notifications to the group delivery AS.
- 17) The group delivery AS aggregates the delivery notifications of the same type from different recipients into a single delivery notification.
- 18) The group delivery AS sends the delivery notification to the S-CSCF.
- 19) The S-CSCF forwards the delivery notification to the UE.
- 20-22) Acknowledgement of the delivery notification is forwarded by S-CSCF to IP-SM-GW.

Annex B: Relationship between SMSIP and SMS-IM Interworking

This annex applies to the architecture option described in clause 7.2.1.1.

The Service Level Interworking Functionality uses a very similar architecture to the one used for the SMSIP functionality. The two functionalities may be co-located as described in the architecture options in clause 7. However each one of those functions is responsible for handling messages in different circumstances.

The key issue is how the S-CSCF handles an Instant Message received from a user.

It is the S-CSCF that needs to invoke the correct Application server based on unambiguous criteria.

Two Application Servers in the network may be called upon to handle an Instant Message:

- the IM AS;
- the IP-SM-GW AS.

The following flowchart explains how an Instant Message received from an IMS subscriber is handled in the network based and which Application Server should be invoked to handle the message.

When the originating S-CSCF receives an Instant Message from an originating UE, it should determine the required handling by checking the content type of the message.

If the content type indicates that it is an encapsulated SMS message (content type = application/vnd.3gpp.sms) as described in TS 24.341 [12], the message is routed to the IP-SM-GW for handling.

If not, the Instant Message maybe sent to the IM AS.

NOTE 1: The iFC could be something different such as the feature tag registered by the client.

At the IM AS, after originating services are executed, the InstantMessage is sent back to the S-CSCF for routeing.

The S-CSCF executes a DNS/ENUM lookup to find the SIP address of the recipient. If the S-CSCF finds a SIP address for the recipient, it sends the Instant Message towards the recipient's IMS system for delivery. If not, it will send the message to the IP-SM-GW for interworking.




Figure B.1: routeing on originating side

NOTE 2: If no IM AS is deployed, the steps in the dashed rectangle are omitted.

Routeing on the terminating side:

When the terminating S-CSCF receives an Instant Message, it should determine the required handling by checking the content type of the message.

If the content type indicates that it is an encapsulated SMS message (content type = application/vnd.3gpp.sms) as described in TS 24.341 [12], the message is routed towards the recipient. Note that in the case of the terminating network, this message can only be received from an IP-SM-GW (Scenario 6.4) in TS 23.204 [5].

If not, the Instant Message may be sent to the IM AS.

NOTE 3: The iFC could be something different such as the feature tag registered by the client.

At the IM AS, after terminating services are executed, the Instant Message is sent back to the S-CSCF for routeing.

The S-CSCF routes the Instant M message towards the recipient.

If operator policy or user preferences in the terminating system indicate that the message is to be delivered as SMS, the message is sent to the IP-SM-GW for delivery as SMS.




Figure B.2: Routeing on terminating side

NOTE 4: If no IM AS is deployed, the steps in the dashed rectangle are omitted.

Annex C: Change history

Change history											
Date	TSG#	TSG Doc.	CR	Rev	Cat	Subject/Comment	Old	New			
2008-03	SP-39	SP-080101	-	-	-	MCC Update for presentation to TSG SA for Approval	1.2.1	2.0.0			
2008-03	SP-39	-	-	-	-	MCC Update after TSG SA approval to Rel-8	2.0.0	8.0.0			